


Role-Based Access Control (RBAC)

ACE Solutions Architecture Technical Team

RBAC: Role-Based Access Control





User Access- CoPilot



≡<	CoPilot						
	Search	User Access Users Permission G	roup Access Management				
⊞	Dashboard	+ User 🍸 🎹 🕹					
0	Cloud Fabric 🗸 🗸	Name	Email	Permission Groups			
ૹ૾૾ૺૺૺ	Networking 🗸 🗸	admin	ace.lab@aviatrix.com	admin			
\mathbf{O}	Security 🗸	copilot_service_account	ace.lab@aviatrix.com	copilot_permission			
(Ø)	SmartGroups	student	ace.lab@aviatrix.com	admin			
ත	Cloud Resources 🗸 🗸		Add User				
8	Monitor 🗸		Username sec-operator				
*	Diagnostics 🗸 🗸		Email				
•	Billing & Cost 🛛 🗸 🗸		sec-team@aviatrix.com				
2	Administration		Password				
	User Access		You can leave it empty and				
	Reports		Confirm Password assign a permission group later				
	Audit		Permission Groups				
錼	Settings 🗸 🗸		1				
▲ aviatrix			Cancel Save				

Aviatrix RBAC Control



≚	CoPilot	User Access	Users	Permission Group	Access Managemen	t
٩	Search	+ Permissi	on Group	7 💷 🕹		
Ψ,	Smartoroups	Name		Copilot Visibility		Controller Permissions
ත	Cloud Resources 🗸 🗸	admin		All		Write
ß	Monitor 🗸	read_only		All		Read
*	Diagnostics 🗸 🗸	copilot_p	ermission	All		Write
O	Billing & Cost 🛛 🗸 🗸	security		All		Security - Write
ą	Administration ^	operation	s	All		Dashboard - Write
	User Access	networkir	g	All		Write
	Reports	Aviatrix D	emo Contro	. All		Write

Permission Sets




Create Permission Group		0
ame Sec-Team		
Sec-realit		
sers		
sec-operator ×		× •
ccess Accounts		
aws_admin × azure-account ×		× •
CoPilot Visibility Controller Pern	ISSIONS	
 CoPilot Visibility is in Preview. Previe environments. 	w features are not safe for deployment	nt in production Learn More
environments.		
Select All Views Clear All	fiews Search and	d Select 🗸
 Cloud Fabric 		
 Networking 		
∧ 🗖 Security		
Distributed Cloud Firewall	All Tabs ×	×v
5/5 Tabs		
Egress	Monitor ×	× •
ThreatIQ		
0/4 Tabs		×
FireNet	All Tabs ×	×v
2/2 Tabs		
Anomaly Detection 1/1 Tabs	All Tabs ×	× •
SmartGroups		

V 🗹 Cloud Fabric
V V Networking
✓ ☑ Security
SmartGroups
✓ ✓ Cloud Resources
V 🗹 Monitor
V Z Diagnostics
V 🗹 Billing & Cost
V dministration
✓ ☑ Settings

Authentication Phase

- Users can be authenticated:
 - Locally on the Aviatrix Controller
 - Onboard Users (Admin, Operators, Developers, Read-Only)
 - Allowed to reset their password
 - Using SAML IDP
 - Onboard Users (Admin, Operators, Developers, Read-Only)
 - Other functionality depends on IDP





Configuring SAML Authentication:

Go to Administration > User Access > Access Management. Under Login Authentication, click +SAML Endpoint.

		User Access Users Permiss	ion Group Access Management			
Dashboard		 Login Authentication 				
Cloud Fabric	~	 Login Authentication 				
Networking	~	SAML				
Security	~	+ SAML Endpoint				۹. Search
SmartGroups		Name	Permission Group	Access Set By	Test	
Cloud Resources	~	aviatrix_saml_sso		profile_attribute	C https://172.64.1.114/flask/saml/lc	/ ā :
Monitor	~					
 Diagnostics 	~					
Billing & Cost	~					
Administration	^					

SAML Endpoint Config			
	guration		
Identity Provider Metadata Type	à		
🔾 URL i Text			
Identity Provider Metadata	URL		
Entity ID			
O Hostname O Custom	۱		
Access Set By			
O Controller 🔘 SAML Id	lentity Provider Attribute	2	
Permission Group			
Sign Auth Requests			
O No			
◯ No			
◯ No			



ACE

Aviatrix Certifier

Authentication



Users can be authenticated Locally or using SAML IDP

			User Acces	ss Users	Permission Group	Access Management		
٩.;	Search							
%	Networking	~	mistory					
0	Security	~			Manage Policy			
(0)	SmartGroups							
�	Cloud Resources	~	^ Log	in Authent	ication			
ß	Monitor	~	SAN	- -				
*	Diagnostics	~	544					
D	Billing & Cost	~	+ 5	SAML Endpoin	t			۹ Search
ŝ	Administration	^	N	ame	Permission Group	Access Set By	Test	
	User Access		a	viatrix_saml_ss	50	profile_attribute	Attps://172.64.1.114/flask/saml/l	ogin/aviatrix_ 🧪 📋 🗄
	Reports							



Next: Design Exercise

